

Pin Tutorial

What is Instrumentation?



A technique that inserts extra code into a program to collect runtime information

Instrumentation approaches:

- Source instrumentation:
 - Instrument source programs
- **Binary instrumentation:**
 - Instrument executables directly

Why use Dynamic Instrumentation?



- ✓ **No need to recompile or relink**
- ✓ **Discover code at runtime**
- ✓ **Handle dynamically-generated code**
- ✓ **Attach to running processes**



Advantages of Pin Instrumentation

Easy-to-use Instrumentation:

- Uses dynamic instrumentation
 - Do not need source code, recompilation, post-linking

Programmable Instrumentation:

- Provides rich APIs to write in C/C++ your own instrumentation tools (called Pintools)

Multiplatform:

- Supports x86, x86-64, Itanium, Xscale
- Supports Linux, Windows, MacOS

Robust:

- Instruments real-life applications: Database, web browsers, ...
- Instruments multithreaded applications
- Supports signals

Efficient:

- Applies compiler optimizations on instrumentation code



Using Pin

Launch and instrument an application

```
$ pin -t pintool -- application
```

Instrumentation engine
(provided in the kit)

Instrumentation tool
(write your own, or use one
provided in the kit)

Attach to and instrument an application

```
$ pin -t pintool -pid 1234
```



Pin Instrumentation APIs

Basic APIs are architecture independent:

- Provide common functionalities like determining:
 - Control-flow changes
 - Memory accesses

Architecture-specific APIs

- e.g., Info about segmentation registers on IA32

Call-based APIs:

- Instrumentation routines
- Analysis routines

Instrumentation vs. Analysis



Concepts borrowed from the ATOM tool:

Instrumentation routines define where instrumentation is **inserted**

- e.g., before instruction
- ☞ **Occurs *first time* an instruction is executed**

Analysis routines define what to do when instrumentation is **activated**

- e.g., increment counter
- ☞ **Occurs *every time* an instruction is executed**

Pintool 1: Instruction Count



```
sub $0xff, %edx
    counter++;
cmp %esi, %edx
    counter++;
jle <L1>
    counter++;
mov $0x1, %edi
    counter++;
add $0x10, %eax
    counter++;
```

Pintool 1: Instruction Count Output



```
$ /bin/ls
```

Makefile imageload.out itrace proccount
imageload inscount0 atrace itrace.out

```
$ pin -t inscount0 -- /bin/ls
```

Makefile imageload.out itrace proccount
imageload inscount0 atrace itrace.out

Count 422838

ManualExamples/inscount0.cpp



```
#include <iostream>
#include "pin.h"

UINT64 icount = 0;

void docount() { icount++; }

void Instruction(INS ins, void *v)
{
    I
}

void Fini(INT32 code, void *v)
{
    std::cerr << "Count " << icount << endl;
}

int main(int argc, char * argv[])
{
    PIN_Init(argc, argv);
    INS_AddInstrumentFunction(Instruction, 0);
    PIN_AddFiniFunction(Fini, 0);
    PIN_StartProgram();
    return 0;
}
```

analysis routine

Same source code works on the 4 architectures

Pin automatically saves/restores application state

Pintool 2: Instruction Trace



```
Print(ip);
sub $0xff, %edx
Print(ip);
cmp %esi, %edx
Print(ip);
jle <L1>
Print(ip);
mov $0x1, %edi
Print(ip);
add $0x10, %eax
```

Need to pass ip argument to the analysis routine (printip())

Pintool 2: Instruction Trace Output



```
$ pin -t itrace -- /bin/ls
```

Makefile imageload.out itrace proccount
imageload inscount0 atrace itrace.out

```
$ head -4 itrace.out
```

0x40001e90
0x40001e91
0x40001ee4
0x40001ee5

ManualExamples/itrace.cpp



```
#include <stdio.h>
#include "pin.H"
FILE * trace;
void printip(void *ip) { fprintf(trace, "%p\n", ip); } argument to analysis routine
void Instruction(INS ins, void *v) { analysis routine
    INS_InsertCall(ins, IPOINT_BEFORE, (AFUNPTR)printip,
                  IARG_INST_PTR, IARG_END);
}
void Fini(INT32 code, void *v) { fclose(trace); }
int main(int argc, char * argv[]) {
    trace = fopen("itrace.out", "w");
    PIN_Init(argc, argv);
    INS_AddInstrumentFunction(Instruction, 0);

    PIN_AddFiniFunction(Fini, 0);
    PIN_StartProgram();
    return 0;
}
```



Examples of Arguments to Analysis Routine

IARG_INST_PTR

- **Instruction pointer (program counter) value**

IARG_UINT32 <value>

- **An integer value**

IARG_REG_VALUE <register name>

- **Value of the register specified**

IARG_BRANCH_TARGET_ADDR

- **Target address of the branch instrumented**

IARG_MEMORY_READ_EA

- **Effective address of a memory read**


And many more ... (refer to the Pin manual for details)

Instrumentation Points



Instrument points relative to an instruction:

- Before (*IPOINT_BEFORE*)
- After:
 - Fall-through edge (*IPOINT_AFTER*)
 - Taken edge (*IPOINT_TAKEN_BRANCH*)



Instrumentation Granularity



Instrumentation can be done at three different granularities:

- Instruction
- Basic block
 - A sequence of instructions terminated at a control-flow changing instruction
 - Single entry, single exit
- Trace
 - A sequence of basic blocks terminated at an unconditional control-flow changing instruction
 - Single entry, multiple exits

```
sub    $0xff, %edx
cmp    %esi, %edx
jle    <L1>
```

```
mov    $0x1, %edi
add    $0x10, %eax
jmp    <L2>
```

1 Trace, 2 BBs, 6 insts

Recap of Pintool 1: Instruction Count



```
counter++;  
sub $0xff, %edx  
counter++;  
cmp %esi, %edx  
counter++;  
jle <L1>  
counter++;  
mov $0x1, %edi  
counter++;  
add $0x10, %eax
```

Straightforward, but the counting can be more efficient

Pintool 3: Faster Instruction Count



```
counter += 3  
sub $0xff, %edx
```

```
cmp %esi, %edx
```

```
jle <L1>
```

```
counter += 2  
mov $0x1, %edi
```

```
add $0x10, %eax
```

basic blocks (bbl)



ManualExamples/inscount1.cpp

```
#include <stdio.h>
#include "pin.H"
UINT64 icount = 0;
void docount(INT32 c) { icount += c; }           analysis routine
void Trace(TRACE trace, void *v) { instrumentation routine
    for (BBL bbl = TRACE_BblHead(trace);
        BBL_Valid(bbl); bbl = BBL_Next(bbl)) {
        BBL_InsertCall(bbl, IPOINT_BEFORE, (AFUNPTR)docount,
                        IARG_UINT32, BBL_NumIns(bbl), IARG_END);
    }
}
void Fini(INT32 code, void *v) {
    fprintf(stderr, "Count %lld\n", icount);
}
int main(int argc, char * argv[]) {
    PIN_Init(argc, argv);
    TRACE_AddInstrumentFunction(Trace, 0);
    PIN_AddFiniFunction(Fini, 0);
    PIN_StartProgram();
    return 0;
}
```



Modifying Program Behavior

Pin allows you not only to observe but also change program behavior

Ways to change program behavior:

- Add/delete instructions
- Change register values
- Change memory values
- Change control flow



Instrumentation Library

```
#include <iostream>
#include "pin.H"

UINT64 icount = 0;

VOID Fini(INT32 code, VOID *v) {
    std::cerr << "Count " << icount << endl;
}

VOID docount() {
    icount++;
}

VOID Instruction(INS ins, VOID *v)
{
    INS_InsertCall(ins, IPOINT_BEFORE,
                  (AFUNPTR)docount);
}

int main(int argc, char * argv[])
{
    PIN_Init(argc, argv);
    INS_AddInstrumentFunction(Instruction,
                             (IPOINT)0,
                             sizeof(INS));
    PIN_AddFiniFunction(Fini, 0);
    PIN_StartProgram();
    return 0;
}
```

Instruction counting Pin Tool

```
#include <iostream>
#include "pin.H"
#include "instlib.H"

INSTLIB::ICOUNT icount;

VOID Fini(INT32 code, VOID *v) {
    cout << "Count" << icount.Count() << endl;
}

int main(int argc, char * argv[]) {
    PIN_Init(argc, argv);
    PIN_AddFiniFunction(Fini, 0);
    icount.Activate();
    PIN_StartProgram();
    return 0;
}
```



Useful InstLib abstractions

- **ICOUNT**
 - # of instructions executed
- **FILTER**
 - Instrument specific routines or libraries only
- **ALARM**
 - Execution count timer for address, routines, etc.
- **FOLLOW_CHILD**
 - Inject Pin into new process created by parent process
- **TIME_WARP**
 - Preserves RDTSC behavior across executions
- **CONTROL**
 - Limit instrumentation address ranges

Useful InstLib ALARM Example





Debugging Pintools

1. Invoke gdb with your pintool (don't "run")

```
$ gdb inscount0  
(gdb)
```

2. In another window, start your pintool with the "-pause_tool" flag

```
$ pin -pause_tool 5 -t inscount0 -- /bin/ls  
Pausing to attach to pid 32017
```

3. Go back to gdb window:


- a) Attach to the process
- b) "cont" to continue execution; can set breakpoints as usual

```
(gdb) attach 32017  
(gdb) break main  
(gdb) cont
```


Pin Overhead



SPEC Integer 2006



Adding User Instrumentation





Instrumentation Driven Simulation

Fast exploratory studies

- Instrumentation \sim = native execution
- Simulation speeds at MIPS

Characterize complex applications

- E.g. Oracle, Java, parallel data-mining apps

Simple to build instrumentation tools

- Tools can feed simulation models in real time
- Tools can gather instruction traces for later use



Performance Models

Branch Predictor Models:

- PC of conditional instructions
- Direction Predictor: Taken/not-taken information
- Target Predictor: PC of target instruction if taken

Cache Models:


- Thread ID (if multi-threaded workload)
- Memory address
- Size of memory operation
- Type of memory operation (Read/Write)

Simple Timing Models:

- Latency information



Branch Predictor Model



BPSim Pin Tool

- Instruments all branches
- Uses API to set up call backs to analysis routines

Branch Predictor Model:

- Detailed branch predictor simulator

BP Implementation

ANALYSIS

```
BranchPredictor myBPU;

VOID ProcessBranch(ADDRINT PC, ADDRINT targetPC, bool BrTaken) {
    BP_Info pred = myBPU.GetPrediction( PC );
    if( pred.Taken != BrTaken ) {
        // Direction Mispredicted
    }
    if( pred.predTarget != targetPC ) {
        // Target Mispredicted
    }
    myBPU.Update( PC, BrTaken, targetPC );
}
```

INSTRUMENT

```
VOID Instruction(INS ins, VOID *v)
{
    if( INS_IsDirectBranchOrCall(ins) || INS_HasFallThrough(ins) )
        INS_InsertCall(ins, IPOINT_BEFORE, (AFUNPTR) ProcessBranch,
                      ADDRINT, INS_Address(ins),
                      IARG_UINT32, INS_DirectBranchOrCallTargetAddress(ins),
                      IARG_BRANCH_TAKEN, IARG_END);
}
```

MAIN


```
int main() {
    PIN_Init();
    INS_AddInstrumentationFunction(Instruction, 0);
    PIN_StartProgram();
}
```




Branch Predictor Performance - GCC



Bimodal not chosen



Bimodal In McFarling Predictor



McFarling Predictor

Branch prediction accuracies range from 0-100%

Branches are hard to predict in some phases

- Can simulate these regions alone by fast forwarding to them in real time



Performance Model Inputs

Branch Predictor Models:

- PC of conditional instructions
- Direction Predictor: Taken/not-taken information
- Target Predictor: PC of target instruction if taken


Cache Models:

- Thread ID (if multi-threaded workload)
- Memory address
- Size of memory operation
- Type of memory operation (Read/Write)

Simple Timing Models:

- Latency information

Cache Simulators



Cache Pin Tool

- Instruments all instructions that reference memory
- Use API to set up call backs to analysis routines

Cache Model:

- Detailed cache simulator

Cache Implementation



ANALYSIS

INSTRUMENT

MAIN

```
CACHE_t CacheHierarchy[MAX_NUM_THREADS][MAX_NUM_LEVELS];

VOID MemRef(int tid, ADDRINT addrStart, int size, int type) {
    for(addr=addrStart; addr<(addrStart+size); addr+=LINE_SIZE)
        LookupHierarchy( tid, FIRST_LEVEL_CACHE, addr, type);
}

VOID LookupHierarchy(int tid, int level, ADDRINT addr, int accessType) {
    result = cacheHier[tid][cacheLevel]->Lookup(addr, accessType );
    if( result == CACHE_MISS ) {
        if( level == LAST_LEVEL_CACHE ) return;
        LookupHierarchy(tid, level+1, addr, accessType);
    }
}

VOID Instruction(INS ins, VOID *v)
{
    if( INS_IsMemoryRead(ins) )
        INS_InsertCall(ins, IPOINT_BEFORE, (AFUNPTR) MemRef,
                      IARG_THREAD_ID, IARG_MEMORYREAD_EA, IARG_MEMORYREAD_SIZE,
                      IARG_UINT32, ACCESS_TYPE_LOAD, IARG_END);
    if( INS_IsMemoryWrite(ins) )
        INS_InsertCall(ins, IPOINT_BEFORE, (AFUNPTR) MemRef,
                      IARG_THREAD_ID, IARG_MEMORYWRITE_EA, IARG_MEMORYWRITE_SIZE,
                      IARG_UINT32, ACCESS_TYPE_STORE, IARG_END);
}

int main() {
    PIN_Init();
    INS_AddInstrumentationFunction(Instruction, 0);
    PIN_StartProgram();
}
```



Performance Models

Branch Predictor Models:

- PC of conditional instructions
- Direction Predictor: Taken/not-taken information
- Target Predictor: PC of target instruction if taken

Cache Models:

- Thread ID (if multi-threaded workload)
- Memory address
- Size of memory operation
- Type of memory operation (Read/Write)

Simple Timing Models:

- Latency information



Simple Timing Model

Assume 1-stage pipeline

- T_i cycles for instruction execution

Assume branch misprediction penalty

- T_b cycles penalty for branch misprediction

Assume cache access & miss penalty

- T_l cycles for demand reference to cache level l
- T_m cycles for demand reference to memory


$$\text{Total cycles} = \alpha T_i + \beta T_b + \sum_{l=1}^{\text{LLC}} A_l T_l + \eta T_m$$

α = instruction count; β = # branch mispredicts ;

A_l = # accesses to cache level l ; η = # last level cache (LLC) misses



Performance - GCC




Several phases of execution

- Important to pick the correct phase of execution



Performance – AMMP



One loop (3 billion instructions) is representative

- High miss rate at beginning; exploits locality at end

Knobs- Getting command arguments to your PIN tool



Example declarations:

```
KNOB<string> KnobOutputFile(KNOB_MODE_WRITEONCE,  
    "pintool", "o", "dcache.out", "specify dcache file name");  
  
KNOB<BOOL> KnobTrackLoads(KNOB_MODE_WRITEONCE,  
    "pintool", "l", "0", "track individual loads -- increases  
    profiling time");  
  
KNOB<UINT32> KnobThresholdMiss  
    (KNOB_MODE_WRITEONCE, "pintool", "m", "100", "only  
    report memops with miss count above threshold");
```

-m # is the command flag to the pin tool
100 is the default value
“only report...” usage of that parm

Knobs- Getting command arguments to your PIN tool



Example knob use:

```
TrackLoads= KnobTrackLoads.Value();
```

```
if( TrackLoads )  
{  
}  
}
```